

Update procedure Grundig DP1 and M1

Your navigation device can be updated as new software versions become available. An update will become available once every year.

The updating procedure can be found below:

1. Please start up your navigation device. Make sure that the device is NOT connected to your PC with an USB cable.
2. You require the serial number of your navigation for the updating procedure. You can find the serial number of your device as follows:



3. Please refer to the website <https://partners.mireo.hr/crm> and enter the serial number of your device. Click on 'Find updates'.

Enter your device ID

example	201955123949415434583048485F3000-Z6AEL	example	Find updates
---------	--	---------	--------------

Updates are available for your device.

4. Important notice: A licence file is required for each corresponding (country)map file you want to update. For example: the licence file of the German map has file extension MCP. The map file has file extension CPF. You always require both files to make the map work on your device.

We strongly advise you to both download and update all licences and all maps on your device.

5. Please create 3 temporary folders on the desktop of your PC named 'Mireo Maps', 'Mireo Licence' and 'Mireo Software'.

DP, maps: OSM Europe released on maandag 23 maart 2015

2 [Download all licences for this update](#)

IMPORTANT: Please check the navigation software version on your device. If it's older than 4.78, you'll need to update it as well.

1 [Download software update](#) [Update instructions](#) **please ignore**

6. Please click on [Download software update](#) (option 1 - as displayed above) .
7. Select 'Save as'.
The file named 'Dontpanic-Mireo-WinCE.4.7.8.zip' should be saved in the folder named **'Mireo Software'** (as just created on the desktop of your PC).
8. Please unzip this file. This results in a new folder named 'Dontpanic'.

 Dontpanic-Mireo-WinCE.4.7.8	5-5-2015 9:54	Bestandsmap
---	---------------	-------------


9. The **ZIP** file named Dontpanic –Mireo-WinCE.4.7.8.ZIP can be deleted after this file has been successfully unzipped.

 Dontpanic-Mireo-WinCE.4.7.8.zip	5-5-2015 9:53	WinZip-bestand	78.732 kB
---	---------------	----------------	-----------

10. Please click on [Download all licences for this update](#) (option 2 – as displayed above) .

Select 'Save as'.

The file named 'Licences.zip' should be saved in the folder named **'Mireo Licence'** (as just created on the desktop of your PC).

 licences.zip	5-5-2015 10:02	WinZip-bestand	14 kB
--	----------------	----------------	-------

11. Please unzip this file. This results in a folder that contains all licences.
12. Consequently, the maps of all countries need to be individually downloaded. (option 3 – as displayed below). Please note that all map files of all countries cannot be downloaded in one go.

Please save the map files in the folder named **'Mireo Maps'** (as just created on the desktop of your PC).

Please allow approximately 45 minutes for downloading all maps (depending on the processor of your PC).

File	Version	Size	
Cyprus OS Cell 2014.12	1412.01	5.22 MB	3 download file
Turkey OS Cell 2014.12	1412.01	74.28 MB	download file
Ukraine OS Cell 2014.12	1412.01	79.75 MB	download file
Switzerland OS Cell 2014.12	1412.01	46.81 MB	download file
Sweden OS Cell 2014.12	1412.01	111.46 MB	download file
Spain OS Cell 2014.12	1412.01	179.79 MB	download file
Slovenia OS Cell 2014.12	1412.01	10.60 MB	download file
Slovakia OS Cell 2014.12	1412.01	21.65 MB	download file
Serbia OS Cell 2014.12	1412.01	15.66 MB	download file
Russia European OS Cell 2014.12	1412.01	317.91 MB	download file
Romania OS Cell 2014.12	1412.01	54.88 MB	download file
Portugal OS Cell 2014.12	1412.01	35.43 MB	download file
Poland OS Cell 2014.12	1412.01	158.08 MB	download file
Norway OS Cell 2014.12	1412.01	108.97 MB	download file
Netherlands OS Cell 2014.12	1412.01	147.85 MB	download file
Montenegro OS Cell 2014.12	1412.01	2.86 MB	download file
Moldova OS Cell 2014.12	1412.01	5.80 MB	download file
Malta OS Cell 2014.12	1412.01	1.07 MB	download file
Macedonia OS Cell 2014.12	1412.01	7.80 MB	download file
Lithuania OS Cell 2014.12	1412.01	22.67 MB	download file
Latvia OS Cell 2014.12	1412.01	24.20 MB	download file
Kosovo OS Cell 2014.12	1412.01	2.57 MB	download file
Italy OS Cell 2014.12	1412.01	204.25 MB	download file
Iceland OS Cell 2014.12	1412.01	6.02 MB	download file
Hungary OS Cell 2014.12	1412.01	27.18 MB	download file
Greece OS Cell 2014.12	1412.01	40.85 MB	download file
Germany OS Cell 2014.12	1412.01	467.96 MB	download file
France OS Cell 2014.12	1412.01	438.86 MB	download file
Finland OS Cell 2014.12	1412.01	100.10 MB	download file
Denmark OS Cell 2014.12	1412.01	53.69 MB	download file
Czech Republic OS Cell 2014.12	1412.01	71.21 MB	download file
Croatia OS Cell 2014.12	1412.01	17.08 MB	download file
Bulgaria OS Cell 2014.12	1412.01	17.66 MB	download file
British Isles OS Cell 2014.12	1412.01	240.35 MB	download file
Bosnia and Herzegovina OS Cell 2014.12	1412.01	20.35 MB	download file
Belgium and Luxembourg OS Cell 2014.12	1412.01	55.42 MB	download file
Belarus OS Cell 2014.12	1412.01	40.05 MB	download file
Austria OS Cell 2014.12	1412.01	73.23 MB	download file
Albania OS Cell 2014.12	1412.01	3.60 MB	download file
Estonia OS Cell 2014.12	1412.01	23.69 MB	download file

13. Please connect your navigation device to your PC with a USB cable and switch on your device. Your PC will detect your device as a new drive.

14. Please click on this drive. The folder 'Dontpanic' will appear. Please select this folder and remove this folder (including content).

15. Please copy the file named 'Dontpanic' (82,6 MB) from the folder named 'Mireo Software' (from the desktop of your PC) to your device. Open the 'Dontpanic' folder on your device and create a new folder named 'Maps'.

Naam	Gewijzigd op	Type	Grootte
Langs	5-5-2015 10:55	Bestandsmap	
Voices	5-5-2015 10:55	Bestandsmap	
Dontpanic	13-3-2015 8:22	Toepassing	6.042 kB
dp.js.cpf	13-3-2015 8:22	CPF-bestand	275 kB
dp.js.mcp	20-3-2015 13:33	MCP-bestand	1 kB
dp.ui.cpf	13-3-2015 8:22	CPF-bestand	1.260 kB
dp.ui.mcp	20-3-2015 13:33	MCP-bestand	1 kB
Maps	5-5-2015 11:02	Bestandsmap	

16. Copy all maps (3,25 GB) from the folder named 'Mireo Maps' (from the desktop on your PC) to the folder named 'Maps'.
17. Copy all licences (7,84 kB) from the folder named 'Mireo Licence' (from the desktop on your PC) to the folder named 'Maps'.
18. The folder 'Maps' should now contain 41 licences (with extension MCP) and 40 maps (with extension CPF) in total.
19. Please disconnect your device from your PC once you have ensured that all data has been successfully copied.

Your device has now been successfully updated.

Remark:

Please note that your device will revert to the default settings after updating the software. This means that the default language and country have to be manually restored again.